

## **Release Notes: Access Professional Edition**

### **Content**

Release Notes: Access Professional Edition.....	1
Patch - Access Professional Edition V3.7, build 3.7.2.3 .....	2
Integration of VSDK 6.32.0099 .....	2
CryptEditTool - Supervisor user.....	2
Update.....	2

## ***Patch - Access Professional Edition V3.7, build 3.7.2.3***

Date: 22.03.2019

Security vulnerabilities have been recently discovered and affect the Access Professional Edition software in terms of video integration and client-server communication.

This patch is according to CVE-2019-6957, CVE-2019-6958.

### **Integration of VSDK 6.32.0099**

Access PE 3.7.2.3 will support VSDK 6.32.0099. By updating to Access PE 3.7.2.3, the cameras will be automatically configured to use "https"-protocol.

If the operator wants to switch off the secure communication, the configuration must be changed manually:

- Open configurator and select "video devices"
- Select a camera and open "Change video device" dialog via edit button or double-click
- Switch "protocol" from "https" to "none"

### **CryptEditTool - Supervisor user**

With Access PE 3.7.2.3, the crypt edit tool has been removed from the setup, together with the now unsupported service user functionality.

The encryption of the configuration files has been changed. The files can no longer be opened with CryptEditTools of older versions.

### ***Update***

Uninstall the previous version of the Access Professional Edition software by following the instructions from the setup menu. Choose to save the data for the new installation (3.7.2.3)

Start the setup for the new patch installation. Follow the instructions from the setup menu and choose to restore the saved data.

If APE SDK is used after the installation of APE 3.7.2.3, the corresponding SDK should be installed as well. If the APE SDK is not installed, the SDK is not able to read the encrypted configuration files.